

# ALP-live (Live-CD/Live-USB) Astra Linux

- :
- /
- 
- 
- deb-
- 
- live-
- 
- ALP-live- 5.4

ALP-live — , (D, DVD, USB-Flash) . . .

USB , CD/DVD . . USB flash drive

i :

- Astra Linux Special Edition .10015-01 ( 1.7), .10015-10
- Astra Linux Special Edition .10015-17
- Astra Linux Special Edition .10015-37 ( 7.7)
- Astra Linux Special Edition .10015-03 ( 7.6)
- Astra Linux Special Edition .10015-01 ( 1.6)  
20200722SE16 ( 6)
- Astra Linux Special Edition .10015-16 . 1  
20201007SE16
- Astra Linux Common Edition 2.12.29

i :

- USB flash drive
- ALP-raw Astra Linux

!

root.

live-build-astra. Astra Linux Special Edition x.7 , Astra Linux Special Edition 1.6 - , Astra Linux Common Edition - - . . .

sudo apt install live-build-astra

sudo live-build-astra -h

Live CD builder

Usage: live-build-astra [OPTIONS]

OPTIONS

- h|--help display this help and exit
- d <distribution> create liveCD of given distribution
- r <url> URL for distribution repo
- i <filename> ISO image(s) to use as a source of packages and other stuff

(without -d, -r and -i options programm will be try to build image for current distribution with first repo from sources.list)

Example-1: live-build-astra

Example-2: live-build-astra -d smolensk -i "/usr/local/tmp/smolensk-current.iso;/usr/local/tmp/devel-smolensk-current.iso"

Example-3: live-build-astra -d orel -r ftp://192.168.0.254/repo

Example-4: live-build-astra -d smolensk -r "ftp://192.168.0.254/repo-main;ftp://192.168.0.254/repo-main-update;ftp://192.168.0.254/repo-devel"

- -d <> - , 1.7\_x86-64, LiveCD;
- -r <url> - URL . , ":" ( ), , - Astra Linux Special Edition 1.7:

 -r "[https://dl.astralinux.ru/astra/stable/1.7\\_x86-64/repository-main/](https://dl.astralinux.ru/astra/stable/1.7_x86-64/repository-main/)"

- Astra Linux ..

- - Astra Linux Special Edition x.7;
- - Astra Linux Special Edition .10015-01 ( 1.6);
- - Astra Linux Common Edition 2.12.

- -i <filename> .iso . , ":" ( ), :

 -i "file1.iso;file2.iso;file3.iso;file4.iso"



4. :

- Astra Linux Special Edition x.7:
  1. ;
  2. ;
  3. ;
  4. ;
- Astra Linux Special Edition .10015-01 ( 1.6) ( ):

  1. ;
  2. ;
  3. ;
  4. ;



, debootstrap Live-. /etc/apt/sources.list , debootstrap live-, .

Live- . , **/etc/apt/sources.list**

/



, , Live-.

, live-, :



/usr/share/live-build-astra/customize/shrink.roster



/usr/share/live-build-astra/customize/astra\_extend.list

( ).



, /usr/share/live-build-astra/customize/astra\_extend.list, shrink.roster, .

```
, sources.list chroot- ) /usr/share/live-build-astra/customize/external_repo.list, . . .
```

## deb-

```
- deb- deb- /usr/share/live-build-astra/customize/extr_pkgs.
```



```
, , /usr/share/live-build-astra/customize/external_repo.list, :
```

```
# Attention! Addition external repo can destroy validity of build live-disk
# Example:
# deb [trusted=yes] https://artifacts.elastic.co/packages/7.x/apt stable main
deb [trusted=yes] http://ftp.debian.org/debian stable main contrib non-free
```

```
, - , x86-64:
```

```
deb ftp://1.2.3.4/frozen/alse-X.7/4.7/4.7.5.1/base-repository 4.7_arm huawei1
deb ftp://1.2.3.4/frozen/alse-X.7/4.7/4.7.5.1/base-repository 4.7_arm main contrib non-free huawei1
```

```
, , /usr/share/live-build-astra/customize/astra_extend.list, . . .
```

## live-

```
live-iso /opt/live_CD.
```

```
build.log, . . .
```

```
1
```

```
ISO- (, /etc/apt/sources.list).
```



```
/etc/apt/sources.list, . . .
```

```
sudo live-build-astra
```

```
2
```

```
, , /etc/apt/sources.list, . . .
```

- -d <distribution> – (1.7\_x86-64, orel, smolensk .);
- -i <filename> – ISO- ;  
ISO- , ":"
- -r <url> – URL ;  
URL , ":"

```
, Astra Linux Special Edition 1.7 iso, . . .
```

```
sudo live-build-astra -d 1.7_x86-64 -i "/usr/local/tmp/1.7-main.iso;/usr/local/tmp/1.7-base.iso"
```

! iso url , debootstrap live-

3

Astra Linux Special Edition .10015-01 ( 1.7) :

```
sudo live-build-astra -d 1.7_x86-64 -i "/tmp/1.7-bin.iso;/tmp/1.7-update-bin.iso;/tmp/1.7-update-base.iso;/tmp/1.7-ext.iso"
```

4

Astra Linux Special Edition .10015-01 ( 1.7) - :

```
sudo live-build-astra -d 1.7_x86-64 -r "http://dl.astralinux.ru/astra/stable/1.7_x86-64/repository-main;http://dl.astralinux.ru/astra/stable/1.7_x86-64/repository-update"
```

5

Astra Linux Common Edition -:

```
sudo live-build-astra -d orel -r "http://dl.astralinux.ru/astra/stable/2.12_x86-64/repository"
```

## ALP-live- 5.4

live- Astra Linux .10015-01 ( 1.6) 5.4:

1. [20210730SE16 \( 8\)](#) ;

2. :

```
echo "linux-5.4" | sudo tee -a /usr/share/live-build-astra/customize/astra_extend.list
```

3. Astra Linux Special Edition .10015-01 ( 1.6):

- a. [20211008SE16 \( 9\)](#): ALSE-live-build-169.tar.gz;
- b. [20210730SE16 \( 8\)](#): ALSE-live-build-168.tar.gz;

4. :

```
tar xf ALSE-live-build-*.tar.gz
```

5. /usr/share/live-build-astra/customize/extr\_pkgs:

```
sudo cp ALSE-live-build-168/pool/non-free/l/linux-astra-modules/* /usr/share/live-build-astra/customize/extr_pkgs
```

6. .