

(FS) (ALD)

⋮



:

- Astra Linux Special Edition .10015-01 (1.7), .10015-10
- Astra Linux Special Edition .10015-17
- Astra Linux Special Edition .10015-37 (7.7)
- Astra Linux Special Edition .10015-03 (7.6)
- Astra Linux Special Edition .10152-02 (4.7)
- Astra Linux Special Edition .10015-01 (1.6)
- Astra Linux Special Edition .10015-16 . 1
- Astra Linux Special Edition .10015-16 . 2
- Astra Linux Special Edition .10265-01 (8.1)
- Astra Linux Common Edition 2.12

1. ald-client-fs, , , :

```
sudo apt install ald-client-fs
```

2. , (. [Astra Linux Directory \(ALD\)](#));
3. :

```
sudo ald-client filesrv-init
```



ald-client help:

```
sudo ald-client help
```

ald-client, :

```
sudo ald-client help filesrv-init
```



:

1. (, ,);
2. . , .

,



.

1. ALD :

```
sudo apt install openssh-server rsync
```


2. , (.),:

```
sudo tar --xattrs --acls -cvzf /ald_export_home/s15.tgz  
/ald_export_home/
```

3. ALD ., :

```
sudo rsync /ald_export_home/s15.tgz root@192.168.32.236:/opt/
```

4. :

 Astra Linux Special Edition () :

a. ()-) :

```
echo 1 | sudo tee /parsecfs/unsecure_setxattr
```

b. PARSEC- PARSEC_CAP_UNSAFE_SETXATTR (0x1000) (. [PARSEC](#)). :

```
sudo execaps -c 0x1000 tar .....
```

:

```
sudo execaps -c 0x1000 -- tar --xattrs --xattrs-  
include=security.{PDPL,AUDIT,DEF_AUDIT} --acls -xvf s15.tgz -  
C /
```

c. :

```
echo 0 | sudo tee /parsecfs/unsecure_setxattr
```

d. :

```
pdp-ls -M -R /ald_export_home/
```

Astra Linux Common Edition Astra Linux Special Edition :

```
sudo tar --xattrs --xattrs-include=security.{PDPL,AUDIT,DEF_AUDIT} --  
acls -xvf s15.tgz -C /
```