

Astra Linux Directory

Astra Linux Directory Astra Linux Special Edition 1.2

```
Astra Linux Directory (ALD) . , ALD LDAP, Kerberos 5, CIFS , , . ALD :  
-ald-client — ALD. ald-client -renew-tickets. , ;  
-ald-admin — ald-admin ALD. , ALD. ;  
-ald-server — ALD. ald-init. . ald-admin , , man .  
ALD, :  
-ald-client-parsec — , ALD; -ald-admin-parsec — ALD;  
-ald-server-parsec — , ALD;  
, . fly-admin-ald, (. ).
```

```
ALD . ALD /etc/ald/ald.conf. commit-config , :  
ald-init commit-config ()  
ald-client commit-config ()  
:= #  
ALD :
```

```
- VERSION — 1.3; - DOMAIN — . :.example.ru
```

```
ALD. , :
```

```
ald-init init
```

```
:
```

```
ald-init backup-ldif  
ald-init restore-backup-ldif
```

```
;
```

```
- SERVER — ALD.
```

```
my-server.example.ru MINIMUM_UID  
. /etc/passwd /etc/shadow.
```



```
MINIMUM_UID 1000;
```

```
- TICKET_MAX_LIFE=10h — Kerberos( ). :NNd(), NNh(), NNm().  
. . . , kinit . , ( ). ald-renew-ticket.  
. , 30d. ;  
- TICKET_MAX_RENEWABLE_LIFE=7d — Kerberos. :NNd(), NNh(), NNm().  
. , TICKET_MAX_LIFE.
```



```
TICKET_MAX_LIFE TICKET_MAX_RENEWABLE_LIFE , ald.conf ;
```

```
- NETWORK_FS_TYPE — . :  
- none — . . .(, , );  
- cifs — Samba/CIFS;
```

```
- SERVER_EXPORT_DIR — ( ). . . Samba/CIFS;
- CLIENT_MOUNT_DIR — ;
- SERVER_FS_KRB_MODES — ( ). Samba/CIFS ( ) . :
- krb5 — Kerberos-;
- krb5i — (integrity) () .
;
- CLIENT_FS_KRB_MODE — Kerberos- . : krb5 krb5i;
- SERVER_ON — /. 0 1.
 SERVER_ON=0, CLIENT_ON=0. SERVER_ON=0.:
- ;— LDAP nsswitch.conf; — Kerberos (allow_tickets=0); — LDAP, Samba, Kerberos, nss-ldapd ; — nsqd ;
- CLIENT_ON — / ALD. 0 1. CLIENT_ON=0.:
- ;— LDAP nsswitch.conf; — nsqd .

/etc/ald/ald.conf:
```

```
VERSION=1.3
DOMAIN=.example.ru
SERVER=my-server.example.ru
MINIMUM_UID=2500
TICKET_MAX_LIFE=10h
TICKET_MAX_RENEWABLE_LIFE=7d
NETWORK_FS_TYPE=cifs
SERVER_EXPORT_DIR=/ald_export_home
CLIENT_MOUNT_DIR=/ald_home
SERVER_FS_KRB_MODES=krb5,krb5i
CLIENT_FS_KRB_MODE=krb5i
SERVER_ON=1
CLIENT_ON=1
```