

ALD KVNO



KVNO - (key version number)—, : keytab KVNO,
, KVNO KVNO KDC (KVNO).



:

- Astra Linux Special Edition .10015-01 .10015-10 (1.7)
- Astra Linux Special Edition .10152-02 (4.7)
- Astra Linux Special Edition .10015-01 (1.6)
- Astra Linux Special Edition .10015-01 (1.5)
- Astra Linux Special Edition .10015-16 . 1 . 2
- Astra Linux Special Edition .10265-01 (8.1)
- Astra Linux Common Edition 2.12

:

1. :

```
sudo ald-init stop  
sudo ald-init backup
```

2. ,, .ald :

```
mkdir ~/.ald
```

3. /var/lib/ald/aldd.keytab /etc/ald/ald.conf :

```
sudo cp /var/lib/ald/aldd.keytab /etc/ald/ald.conf ~/.ald/
```

4. ():

```
sudo ald-init init
```

5. :

```
sudo ald-init restore-backup
```

6. keytab :

```
sudo cp ~/.ald/aldd.keytab /var/lib/ald/  
sudo ald-init start
```

, , /etc/ald/ald.conf.

7. :

```
ald-admin test-integrity
```