

«» , .

 .:

 :

Astra Linux Special Edition .10015-01 (1.7), .10015-10
Astra Linux Special Edition .10015-17
Astra Linux Special Edition .10015-37 (7.7)
Astra Linux Special Edition .10015-03 (7.6)
Astra Linux Special Edition .10015-01 (1.6)
Astra Linux Special Edition .10015-16 . 1
Astra Linux Common Edition 2.12

, :

1. (Ctrl-Alt-F1);
2. , .
3. xrandr , , () , :

xrandr

```
Screen 0: minimum 320 x 200, current 1024 x
768, maximum 8192 x 8192
DVI-I-1 disconnected primary (normal left
inverted right x axis y axis)
HDMI-1 disconnected (normal left inverted right
x axis y axis)
VGA-1 connected 1024x768+0+0 (normal left
inverted right x axis y axis) 477mm x 268mm
1920x1080 60.00 + 59.96 59.93
...
```

, (DVI-I-1, HDMI-1 VGA-1), :

- VGA-1;
- DVI-I-1 HDMI-1 ;
- DVI-I-1 (primary).

4. (VGA-1), . /etc/X11/fly-dm/Xsetup :

```
xrandr --output VGA-1 --primary
xrandr --output DVI-I-1 --off
xrandr --output HDMI-1 --off
```

5. :

```
sudo systemctl restart fly-dm
```

6. Ctrl+Alt+F7.

 / fly-dm fly-qdm.