

# Astra Linux Special Edition 1.5      USB-

!      . . [Astra Linux](#).

i      :

- Astra Linux Special Edition .10015-01 ( 1.5)

• USB-  
• -


USB-

!      ( ID\_SERIAL)      udev      .

!      USB-, ,      floppy fuse.  
fuse      samba .      samba ,      ,: USB-      ntfs      suid      /bin/ntfs-3g.


!      Astra Linux      fuse .      USB-      .      [Astra Linux](#).

, . USB-      Ext2/Ext3/Ext4.  
fly-admin-smc ( ), " " , " " "+" (" " ").  
(. ).      ( 1)




- "", "" (2)

2.




"" , ( ) - , , (3)

3.



"" ( )



EXT- Astra Linux , ACL. . :

1. :

```
mkdir /tmp/ext
```

2. :

```
mount /dev/sdb3 /tmp/ext/
```

3. (.):

```
chown <_>.<_> /tmp/ext/
```

4. :

```
chmod 770 /tmp/ext/
```

5. :

```
umount /dev/sdb3
```

-

1. Ext2 ;
2. (Label), : ns, dsp, sec, ss;
3. , ID\_SERIAL\_SHORT ID\_FS\_UUID, , ;
4. , .