

# Astra Linux:

- - 
  - **digsig\_verif**
    - **fly-admin-smc**
    - **astra-digsig-control**
    - **/etc/digsig/**
      - **/etc/digsig/digsig\_initramfs.conf**
      - 
      -
  - 
  - **fly-admin-smc**
  - - 
    -



:

- Astra Linux Special Edition .10015-01 ( 1.7) 5.4
- Astra Linux Special Edition .10015-01 ( 1.6) 5.4
- Astra Linux Special Edition .10015-16 .1



5.4

,

.

() () . Astra Linux ( digsig\_verif), () . :

- ELF ( ) - , ( - );
- - , ( - );

**ELF**, , .

() () :

1. ( bash). . **astra-interpreters-lock** **astra-safepolicy**. , , .
2. bash.
3. .
4. -2 -2 ( . -2: **parsec-kiosk2** () .

:

:

1. ( bash). :

```
sudo astra-interpreters-lock enable
```

2. bash. :

```
sudo astra-bash-lock enable
```

3. . :

```
sudo astra-nochmodx-lock enable
```

4. :
  - a. ( bash):

```
sudo astra-interpreters-lock status
```

"" ;

```
sudo astra-interpreters-lock is-enabled
```

"" .

b. bash:

```
sudo astra-bash-lock status  
"  
sudo astra-bash-lock is-enabled  
"
```

c. :

```
sudo astra-nochmodx-lock status  
"  
sudo astra-nochmodx-lock is-enabled  
"
```

5. -2  
a. -2.:

```
echo 1 | sudo tee /sys/module/parssec/parameters/uc_enforce
```

b. .:

```
echo 1 | sudo tee /sys/module/parssec/parameters/uc_complain;
```

c. -2 .:

```
echo 1 | sudo tee /etc/parssec/kiosk2_enforce; echo 1 | sudo tee  
/etc/parssec/kiosk2_complain;
```

:

1. : - - - - :

```
sudo fly-admin-smc
```

2. - :

3. :  
a. " Bash ".  
b. " Bash ".

4.

5. , " , , ":"

:

• :

```
sudo reboot
```

• - - .

digsig\_verif

## fly-admin-smc

```
fly-admin-smc . fly-admin-local, :<> — — — >>. fly-admin-smc fly-admin-digsig .
```

## astra-digsig-control

```
astra-digsig-control astra-safepolicy.
```

/etc/digsig/

### /etc/digsig/digsig\_initramfs.conf

```
/etc/digsig/digsig_initramfs.conf.
```

!, /etc/digsig ( —, /etc/digsig/digsig\_initramfs.conf) :

1. :

```
sudo update-initramfs -u -k all
```

2. .

!, /etc/digsig .

<\_>= <\_>

#### • DIGSIG\_ELF\_MODE — ELF. :

- 0 — . . ;
- 1 — . . , , ;
- 2 — . . , , ' , ' ;

#### • DIGSIG\_XATTR\_MODE — . . :

- 0 — . . ;
- 1 — . . , , ;
- 2 — . . , , ' , ' ;

#### • DIGSIG\_IGNORE\_XATTR\_KEYS — :

- 0 — . . ;
- 1 — . . ;

#### • DIGSIG\_IGNORE\_GOST2001 — ~~34.10-2001:

- 0 — . ~~34.10-2001 ;
- 1 — ~~34.10-2001 ;

/etc/digsig/digsig\_initramfs.conf /etc/digsig/ :

- /etc/digsig/keys — . . ;
- /etc/digsig/xattr\_control — . . . . ;
- /etc/digsig/xattr\_keys — . . ;

/etc/digsig/xattr\_control . . . . :

- . . slash ( , "/" );
- , . slash ("//"), . . : //bin/script.sh;
- , . slash, . . ( ) . : /bin/;
- , . /bin/script : /bin/script, /bin/script.signed, /bin/script12345 ..

```
sysfs. :  
● , , , ramfs . /etc/digsig ;  
● , (""");  
● , .. (""");  
● (, ) , , ;  
● , , ;  
● , , ;  
  
, :  
  
● :  
○ /sys/digsig/elf_mode — . DIGSIG_ELF_MODE
```

1, , . . . :

```
sudo cp /etc/digsig/build_system_rbt_root_key_2018.gpg /sys  
/digsig/keys
```

- /sys/digsig/xattr\_mode — . DIGSIG\_XATTR\_MODE;
- /sys/digsig/ignore\_gost2001 — ~34.10-2001. DIGSIG\_IGNORE\_GOST2001;
- /sys/digsig/ignore\_xattr\_keys — . DIGSIG\_IGNORE\_XATTR\_KEYS;

• :

- /sys/digsig/keys — ;
- /sys/digsig/xattr\_control — , ;
- /sys/digsig/xattr\_keys — , ;

```
sudo cat /sys/digsig/<_>
```

```
sudo cat /sys/digsig/elf_mode /sys/digsig/xattr_mode
```

digsig\_verify , :

- ;
- , /etc/digsig/keys.
- , — ;
- /etc/digsig/keys() — ;
- /etc/digsig/keys\_xattrs() — , , . ..

(.). gnupg --export/etc/digsig/keys ;

., ,  
/etc/digsig/keys/, /etc/digsig/xattr\_keys

```
sudo cp /<*>/<*> /etc/digsig/keys/
```

/etc/diagsig/keys

- (`/etc/digsig/keys`)      `digsig verify`:

• ,  
•  
•  
**i** /etc/digsig/keys/key1.gpg — 1, ;  
/etc/digsig/keys/key2.gpg — 2, ;  
/etc/digsig/keys/key1/key1-1.gpg — , 1  
/etc/digsig/keys/key1/key1-2.gpg — , 1  
/etc/digsig/keys/key2/key2-1.gpg — , 2  
/etc/digsig/keys/key2/key2-2.gpg — , 2

, , /etc/digsig/xattr\_keys/.:

```
sudo cp /<>/< > /etc/digsig/xattr_keys/
```

/etc/digsig/xattr\_keys/ , . , (.).

## fly-admin-smc

Astra Linux fly-admin-smc, . : " " " " " " " . ( F1).

ELF

, . GNU Privacy Guard. Astra Linux GnuPG ~34.11-94. :

```
gpg --version
```

1. . .gnupg . fly-admin-amc,

**!** RSA. Astra Linux . Astra Linux GOST\_R34.10-2012.

a. gpg :

```
gpg --full-generate-key
```

GOST\_R34.10-2012. :

```
pub gP256 2024-03-12 [SC]  
566F70D5D822D1B51B23CBE60055EBA236DA8851  
uid Astra Linux <info@astralinux.ru>
```

- , 566F70D5D822D1B51B23CBE60055EBA236DA8851. ;

b. :  
i. , :

```
Key-Type:GOST_R34.10-2012  
%no-protection  
Name-Real:<_>  
Name-Comment: <>  
Name-Email: <e-mail>
```

i. . Unattended GPG key generation;

ii. :

```
gpg --gen-key --batch <____>
```

iii. :

```
gpg --list-keys
```

2. . :

```
gpg --export <_> | sudo gpg --import  
sudo gpg --sign-key <_>
```

/etc/digsig/xattr\_keys. :

```
sudo gpg --export <_> | sudo tee /etc/digsig/xattr_keys/<____>
```



.. :

```
sudo gpg --export <_> | sudo tee /etc/digsig/xattr_keys/<____>
```

3. /etc/digsig/xattr\_control . :

/bin/spo

"/", , ..

4. . :



, ..

```
bsign --sign --xattr <_>
```

bsign;

5. . :

a. DIGSIG\_XATTR\_MODE /etc/digsig/digsig\_initramfs.conf, ;  
b. :

```
sudo update-initramfs -u -k all
```

c. ;

bsign:

```
bsign -w <_>
```

```
digsig_verif . :
```

```
sudo dmesg
```

```
, digsig_verif:
```

```
sudo dmesg | grep DIGSIG
```

```
, /var/log/messages /var/log/kernel.log, :
```

```
... DIGSIG: [ERROR] NOT SIGNED: path=....
```