

Astra Linux Special Edition 1.3: ALD

1. :
 - a. ALD , (,) (, , ..).
 - b. : ..
 - c. ALD " " : ..
 - d. , Kerberos 10 . (- SERVER_PROPAGATE_PERIOD /etc/ald/ald.conf).
2. () :
 - a. ald-server-common:
apt-get install ald-server-common
 - b. LDAP Kerberos :
ald-init init
 - c. /etc/ald/ald.conf, , SERVER_ID , , SERVER_ID=1, - SERVER_ID=2.
 - d. , :
ald-client commit-config --update-keytab
 - e. :
ald-client slavesrv-init
3. :
 - a. , :
ald-client slavesrv-online
 - b. () /etc/ald/ald.conf, SERVER ().
 - c. /etc/ald/ald.conf :
ald-client commit-config

.

:

- dcm.example.org
- fs.example.org
- ac.example.org

- dcs.example.org
dcs.example.org :

ALD:

apt-get install ald-server-common

:

ald-init init

/etc/ald/ald.conf. :

SERVER=dcm.example.org
SERVER_ID=2 #, dcm.example.org 1.

:

ald-client commit-config --update-keytab

:

ald-client slavesrv-init

dcm.example.org dcs.example.org:

dcs.example.org :

ald-client slavesrv-online

fs.example.org ac.example.org:

/etc/ald/ald.conf:

SERVER=dc.example.org

:

ald-client commit-config