

Astra Linux

```
i      ( ), . /etc/power/image_size , . 2
/5 , , (https://www.kernel.org/doc/Documentation
/power/interface.txt), , .

_ _ _ _ _ * _ _
.: (swap): .
```

 :

9. (UUID) , :

```
sudo findmnt -no UUID -T /swap
```

:

 880d582e-5797-4d06-9e33-71da00a7aca2

10.

```
sudo filefrag -v /swap | grep "^s*0:"
```

:

```
0:          0..          0:    7176192..    7176192:          1:
```

```
( - 7176192);
```

11. /etc/initramfs-tools/conf.d/resume (UUID RESUME resume_offset). - :

```
RESUME=UUID=880d582e-5797-4d06-9e33-71da00a7aca2 resume_offset=7176192
```

:

```
echo "UUID=`sudo findmnt -no UUID -T /swap` resume_offset=`sudo  
filefrag -v /swap | grep "^s*0:" | xargs | cut -d " " -f 4 | cut -d . -  
f 1`"
```

12. /etc/default/grub GRUB_CMDLINE_LINUX_DEFAULT, :

```
GRUB_CMDLINE_LINUX_DEFAULT="quiet net.ifnames=0 resume=UUID=880d582e-5797-4d06-9e33-71da00a7aca2  
resume_offset=7176192"
```

13. grub ramfs:

```
sudo update-grub  
sudo update-initramfs -u -k all
```

14. , /etc/fstab . . :

```
UUID=af75b52e-22ab-4429-9de1-8ac700187ba2 none          swap          sw              0              0
```

15. ;

16. , /swap:

```
sudo swapon
```

17. .