

Samba

-
- The diagram illustrates a network topology. A central node labeled 'samba' in blue is connected to five other nodes. These nodes are represented by black dots and open circles. The connections are as follows:
 - A top node (black dot) connects to a middle node (black dot).
 - The middle node connects to the 'samba' node (blue text) and a bottom node (black dot).
 - The 'samba' node connects to a node below it (open circle).
 - This node connects to a node below it (open circle).
 - This node connects to a node below it (open circle).
 - This node connects to a node below it (open circle).
 - This node connects to a node below it (open circle).

- Astra Linux Special Edition .10015-01 (1.7), .10015-10
- Astra Linux Special Edition .10015-17
- Astra Linux Special Edition .10015-37 (7.7)
- Astra Linux Special Edition .10015-03 (7.6)
- Astra Linux Special Edition .10152-02 (4.7)
- Astra Linux Special Edition .10015-01 (1.6)
- Astra Linux Special Edition .10015-16 . 1
- Astra Linux Special Edition .10015-16 . 2
- Astra Linux Special Edition .10265-01 (8.1)
- Astra Linux Common Edition 2.12

samba (MIT Kerberos) Astra Linux, .
 , samba - fly-admin-samba.
 samba Heimdal Kerberos .

```
synaptic, .
fly-admin-samba, samba :
```

```
sudo apt install fly-admin-samba
```

"" > "" > "" > "" (Samba)"

$$\vdots$$

④ "" > "" > "" > "" (Samba)"

samba:

- Kerberos:

 , *

$$\begin{matrix} & \cdot \\ , & \cdot \end{matrix}$$

1. , (, /srv/share):

```
sudo mkdir /srv/share
```

2. 0775 nobody ("") nogroup (""):

```
sudo chown nobody:nogroup /srv/share
sudo chmod 775 /srv/share
```

3. `/etc/samba/smb.conf` :

a. , `[global]` `map to guest`, `Bad User`, - :

```
map to guest = Bad User
```

, , ;

b. :

```
[share]
comment = < >
guest ok = yes
force user = nobody
force group = nogroup
path = /srv/share
read only = no
```



`force user` `force group` `nobody ("")` `nogroup ("")`, , : , , `nobody:nogroup` , .

`read only` :

```
read only = yes
```

4. :

```
testparm
```

5. `samba`, :

```
sudo systemctl restart smb
```

`samba` - `/etc/samba/smb.conf` - .



`/etc/samba/smb.conf`

, `samba (smbd)`, `nbmd`, `netbios`:

```
sudo systemctl restart smbd nbmd
```

`samba`

• , `samba`, ,

```
smbtree
```

, (, .) `samba`, .

- smbclient:
 - hostname:

```
smbclient -L hostname
```

- share hostname:

```
smbclient -N \\\hostname\\share
```

, . help

"" _ " " , , .

.

cifs-utils, , :

```
sudo apt install cifs-utils
```

mount, :

```
sudo mount -t cifs //10.0.10.201/share /mnt -o users,sec=none
```

:

- //10.0.10.201/share - "share" 10.0.10.201
- /mnt -

, , /etc/fstab :



```
//10.0.10.201/share /mnt cifs credentials=/root/.smbclient,rw,nosharesock,vers=1.0,soft,noperm 0 0
```

:

noauto	(mount -a).
credentials=	, samba . : username=samba_user_name password=samba_user_password domain=astra.ru domain , . /etc/fstab (username= password=), , , /etc/fstab , , .

noperm	. , Unix- CIFS (CIFS Unix Extensions), / , . (ACL) , (ACL).
nosharesock	().
rw	.
ro	.
soft	, , , . .
user	.
vers=	SMB. 1.0.

autofs