

ALP-live (Live-CD/Live-USB) Astra Linux

```
•
•
• /
  ○
  ○
  ○ deb-
  ○
  ○ live-
  ○
•
• ALP-live- 5.4
```

 ALP-live — , (D, DVD, USB-Flash) . , .

 , USB , CD/DVD . . [USB flash drive](#)



- Astra Linux Special Edition .10015-01 (1.7), .10015-10
- Astra Linux Special Edition .10015-17
- Astra Linux Special Edition .10015-37 (7.7)
- Astra Linux Special Edition .10015-03 (7.6)
- Astra Linux Special Edition .10015-01 (1.6) [20200722SE16 \(6\)](#)
- Astra Linux Special Edition .10015-16 . 1 [20201007SE16](#)
- Astra Linux Common Edition 2.12.29



- [USB flash drive](#)
- [ALP-raw Astra Linux](#)



root.

live-build-astra. Astra Linux Special Edition x.7 , Astra Linux Special Edition 1.6 - , Astra Linux Common Edition - . :

```
sudo apt install live-build-astra
```

:

```
sudo live-build-astra -h
```

Live CD builder

Usage: live-build-astra [OPTIONS]

OPTIONS

- h|--help display this help and exit
- d <distribution> create liveCD of given distribution
- r <url> URL for distribution repo
- i <filename> ISO image(s) to use as a source of packages and other

stuff

(without -d, -r and -i options program will be try to build image for current distribution with first repo from sources.list)

Example-1: live-build-astra

Example-2: live-build-astra -d smolensk -i "/usr/local/tmp/smolensk-current.iso;/usr/local/tmp/devel-smolensk-current.iso"

Example-3: live-build-astra -d orel -r ftp://192.168.0.254/repo

Example-4: live-build-astra -d smolensk -r "ftp://192.168.0.254/repo-main;ftp://192.168.0.254/repo-main-update;ftp://192.168.0.254/repo-devel"

- -d <> - , 1.7_x86-64, LiveCD;
- -r <url> - URL . , , ";" () , , - Astra Linux Special Edition 1.7:

 -r "https://dl.astralinux.ru/astra/stable/1.7_x86-64/repository-main/"

- Astra Linux .:

- - [Astra Linux Special Edition x.7](#);
- - [Astra Linux Special Edition .10015-01 \(1.6\)](#);
- - [Astra Linux Common Edition 2.12](#).

- -i <filename> .iso . , , ";" () , :

 -i "file1.iso;file2.iso;file3.iso;file4.iso"



4. :

- Astra Linux Special Edition x.7:
 1. ;
 2. ;
 3. ;
 4. ;
- Astra Linux Special Edition .10015-01 (1.6) ():
 1. ;
 2. ;
 3. ;
 4. ;



, debootstrap Live- **/etc/apt/sources.list** , debootstrap live- .

Live- . , **/etc/apt/sources.list**

/



, , Live-.

, live- , :



/usr/share/live-build-astra/customize/shrink.roster

:



/usr/share/live-build-astra/customize/astra_extend.list

().



, /usr/share/live-build-astra/customize/astra_extend.list, shrink.roster, .

, sources.list chroot-) /usr/share/live-build-astra/customize/external_repo.list, . .

deb-

- deb- deb- /usr/share/live-build-astra/customize/extra_pkgs.



, .

, , /usr/share/live-build-astra/customize/external_repo.list, :

```
# Attention! Addition external repo can destroy validity of build live-disk
# Example:
# deb [trusted=yes] https://artifacts.elastic.co/packages/7.x/apt stable main
deb [trusted=yes] http://ftp.debian.org/debian stable main contrib non-free
```

, - , x86-64:

```
deb ftp://1.2.3.4/frozen/alse-X.7/4.7/4.7.5.1/base-repository 4.7_arm huawei1
deb ftp://1.2.3.4/frozen/alse-X.7/4.7/4.7.5.1/base-repository 4.7_arm main contrib non-free huawei1
```

, , /usr/share/live-build-astra/customize/astra_extend.list, . .

live-

live-iso /opt/live_CD.

build.log, .

1

ISO- (, /etc/apt/sources.list).



/etc/apt/sources.list, .

sudo live-build-astra

2

, , /etc/apt/sources.list, :

- -d <distribution> – (1.7_x86-64, orel, smolensk .);
- -i <filename> – ISO- ;
ISO-, ","
- -r <url> – URL ;
URL, ","

, Astra Linux Special Edition 1.7 iso, :

```
sudo live-build-astra -d 1.7_x86-64 -i "/usr/local/tmp/1.7-main.iso;/usr/local/tmp/1.7-base.iso"
```



iso url , debootstrap live-.

3

Astra Linux Special Edition .10015-01 (1.7) :

```
sudo live-build-astra -d 1.7_x86-64 -i "/tmp/1.7-bin.iso;/tmp/1.7-update-bin.iso;/tmp/1.7-update-base.iso;/tmp/1.7-ext.iso"
```

4

Astra Linux Special Edition .10015-01 (1.7) - :

```
sudo live-build-astra -d 1.7_x86-64 -r "http://dl.astralinux.ru/astra/stable/1.7_x86-64/repository-main;http://dl.astralinux.ru/astra/stable/1.7_x86-64/repository-update"
```

5

Astra Linux Common Edition -:

```
sudo live-build-astra -d orel -r "http://dl.astralinux.ru/astra/stable/2.12_x86-64/repository"
```

ALP-live- 5.4

live- Astra Linux .10015-01 (1.6) 5.4:

1. [20210730SE16 \(8\)](#) ;
2. :

```
echo "linux-5.4" | sudo tee -a /usr/share/live-build-astra/customyze/astra_extend.list
```

3. Astra Linux Special Edition .10015-01 (1.6):
 - a. [20211008SE16 \(9\)](#): [ALSE-live-build-169.tar.gz](#);
 - b. [20210730SE16 \(8\)](#): [ALSE-live-build-168.tar.gz](#);

4. :

```
tar xf ALSE-live-build-*.tar.gz
```

5. /usr/share/live-build-astra/customyze/extra_pkgs:

```
sudo cp ALSE-live-build-168/pool/non-free/l/linux-astra-modules/* /usr/share/live-build-astra/customyze/extra_pkgs
```

6. .