

Astra Linux Special Edition 1.5

- [Dell Inspiron 3551](#)
- [Hewlett Packard](#)
- [Tavolga TP-C22](#)
- [TF Volga L10/21.5 /](#)



:

- Astra Linux Special Edition .10015-01 (1.5)

/etc/X11/fly-dm [Xsetup](#)

Xsetup

```
#!/bin/sh
# Xsetup - run as root before the login dialog appears

#xconsole -geometry 480x130-0-0 -notify -verbose -fn fixed -exitOnFail -file /dev/xconsole &

if [ -x /usr/sbin/pdp-flbl ]; then
    find /dev/dri -type c -exec /usr/sbin/pdp-flbl :::ehole {} \;
    find /dev -name nvidia* -type c -exec /usr/sbin/pdp-flbl :::ehole {} \;
    /usr/sbin/pdp-flbl -R :::ehole /proc/driver/nvidia \;
fi

/usr/bin/fly-dm-set-dpi.sh
```

Astra Linux Special Edition 1.3 Intel . . .

:

```
dpkg -i xserver-xorg-video-intel-dbg_2.19.0-6_amd64.deb dpkg -i xserver-xorg-video-intel_2.19.0-6_amd64.deb
```

[xorg_intel_signed.tgz](#)

() [xorg_intel_src.tgz](#)
 [intel_backlight.sh](#).

, , , F2, ESC, pci=conf1

GRUB pci=conf1

Nvidia : DPI (Dots per inch) . , DPI EDID (Extended display identification data) . , .

(, Nvidia):

```
sudo nvidia-xconfig --no-use-edid-dpi
```

X-/etc/X11/xorg.conf, , DPI, EDID :

```
Option "UseEdidDpi" "False"
```

DPI, "Monitor" /etc/X11/xorg.conf :

```
Option "DPI" "96 x 96"
```

96 DPI.

X-. , , :

```
service fly-dm restart
```

SysRq /etc/sysctl.d/10-magic-sysrq.conf :

/etc/sysctl.d/10-magic-sysrq.conf

kernel.sysrq = 0

50-synaptics.conf /usr/share/X11/xorg.conf.d

 [50-synaptics.conf](#)

, , : , . , .

:

/usr/share/X11/xorg.conf.d/10-evdev.conf keyboard, EmulateThirdButton, :

EmulateThirdButton false

, ,
/etc/default/grub :

GRUB_CMDLINE_LINUX_DEFAULT="quiet splash i8042.noloop=1"
GRUB_CMDLINE_LINUX="i8042.noloop=1"