


(

•



◦
◦
◦
◦

Astra Linux fly-admin-dm:

"": "": "": ");



"": "": "": :



AutoLogin* /etc/X11/fly-dm/fly-dmrc. . . :



```
sudo chmod 600 /etc/X11/fly-dm/fly-dmrc
```

- AutoLoginEnable=true
- AutoLoginUser=<_>.
- AutoLoginPass=<_>.

AutoLoginEnable false.

, AutoLoginUser ().

Astra Linux Special Edition / AutoLoginMAC, . . . :



```
AutoLoginMAC=0:0:0x0:0x0!
```

/var/log/fly-dm/Xorg.0.log, :



```
[ 9.484] XPARSEC: Session labeled by 'some_privileged' with label='0:63:0x0:0x0!'
```

, /etc/X11/fly-dm/Xsession, () :

```
# replace default session name if autologin
if [ "$session" = "default" ]; then
    fly-wmfunc FLYWM_GET_TOUCHSCREEN
    if [ $? -eq "0" ]; then
        session="fly-start-tablet"
        export DESKTOP_SESSION="fly-tablet"
    else
        session="fly-wm"
        export DESKTOP_SESSION="fly"
    fi
fi
```

• :

```
        export DESKTOP_SESSION="fly"
```

• :

```
        export DESKTOP_SESSION="fly-tablet"
```

• :

```
export DESKTOP_SESSION="fly-mobile"
```