

# Astra Linux LVM LVM

- Astra Linux LVM
  - LVM
- LVM
  - 
  - 
  -



:

- Astra Linux Special Edition .10015-01 ( 1.6)
- Astra Linux Special Edition .10015-16 .1
- Astra Linux Common Edition 2.12

- Astra Linux Special Edition x.7
- boot LVM.




LVM - (. logical volume manager) — , / .

- (physical volume, pv) — , ( , RAID-);
- (volume group, vg) — pv (, );
- (logical volume, lv) — ; hda1, sdb3 ; .

## Astra Linux LVM

Astra Linux LVM :

1.






! /boot LVM.  
Astra Linux " " , .



! , ( , ).  
, ( ).

2. LVM ( - , . Astra Linux ).

3. ( LVM):



4.

## LVM

LVM :

```
sudo vgs
```

```
VG      #PV #LV #SN
Attr   VSize  VFree
astra-vg 2    4    2    wz--n- 37,75g
12,00g
```

```
astra-vg 37.75GB, 12 ( astra-vg ).
```

LVM ,:

```
sudo lvs
```

LV	VG	Attr	LSize
Pool	Origin	Data%	Meta%
Cpy%	Sync	Convert	
lvsnap	astra-vg	swi-a-s---	4,00
g	root	79,20	
lvsnap2	astra-vg	swi-a-s---	4,00
g	root	75,78	
root	astra-vg	owi-aos---	15,76g
swap_1	astra-vg	-wi-ao----	2,00g

```
root swap_1( " "), root(. Origin) lvsnap lvsnap2, 79.20%
75.78%.
```

## LVM



, , .

```
, ., /dev/sdb:
```

```
sudo pvcreate /dev/sdb
```

:

```
pvs
```

PV	VG	Fmt	Attr
PSize	PFree		
/dev/sda5	astra-vg	lvm2	a-- 17,76g
0			
/dev/sdb	astra-vg	lvm2	a-- 20,00g
12,00g			

```
(/dev/sda5, ( ), /dev/sdb, . . astra-vg).
```

```
- (- ),, vg-astra:
```

```
sudo vgextend astra-vg /dev/sdb
```

:

```
sudo lvcreate -L 4GB -s -n lvsnap
/dev/astra-vg/root
```

- -L 4GB - , .



- , . :
- , ;
- , , , ;
- , , ;

.. : Update 3 Astra Linux Special Edition .10015-01 ( 1.6) 4 79%. , ( - ), ( - ).

- -s - ;
- -n lvsnap - (lvsnap);
- /dev/astra-vg/root - (., ).



- LVM , /etc/lvm/lvm.conf :

- snapshot\_autoextend\_threshold = 100 - , .  
100%, .. ;
- snapshot\_autoextend\_percent = 20 - , , .



1. , , Live- Astra Linux Common Edition ( , ).

2. Live- Astra Linux Common Edition lvm2, :

- a. :
  - i. , ( , DNS, 8.8.8.8) , ;
  - ii. /etc/apt/sources.list ;
  - iii. :

```
sudo apt update
sudo apt install lvm2
```

- b. lvm2 .

3. /dev/astra-vg/lvsnap:

```
sudo lvconvert --merge /dev
/astra-vg/lvsnap
```

4. . . . , . . .