

# faillog sudo



:

- Astra Linux Special Edition .10015-01 ( 1.7)
- Astra Linux Special Edition .10015-01 ( 1.6)

PAM- pam\_tally. pam\_tally auth /etc/pam.d/common-auth .

PAM- sudo common-auth:

```
##PAM-1.0
@include common-auth
@include common-account
@include common-session-noninteractive
```

common-auth pam\_tally:

```
auth [success=ignore default=die] pam_tally.so per_user deny=10
```

(auth) pam\_tally , , attempted login. , pam\_tally account. pam\_setcred. sudo . auth.log warning:

```
Mar 30 14:31:41 dcml4 sudo: pam_tally(sudo:setcred): Tally underflowed for user root
```

PAM- sudo pam\_tally:

```
account required pam_tally.so
```

!  
pam\_tally account auth. :

```
@include common-auth
```

, PAM- sudo attempted logins  
:

```
##PAM-1.0
@include common-auth
@include common-account
@include common-session-noninteractive
account required pam_tally.so
```