

Astra Linux EFISTUB (grub/grub2)

- [Astra Linux](#) [UEFI](#)
- [UEFI- grub2](#)
- [UEFI](#)
- [UEFI](#)
 - [Virtual Machine Manager](#)
 - [Oracle VirtualBox](#)



:

1. KVM, :
"UEFI x84_64 /usr/share/OVMF/OVMF_CODE_4m.fd"
2. VirtualBox "EFI (OC)". , .
"UEFI x84_64 /usr/share/OVMF/OVMF_CODE.fd";



:

- Astra Linux Special Edition .10015-01 (1.6)
- Astra Linux Special Edition .10015-16 . 1
- Astra Linux Special Edition .10015-01 (1.5)
- Astra Linux Common Edition 2.12



SecureBoot . [Astra Linux](#) [SecureBoot](#)

Astra Linux UEFI

Astra Linux , UEFI, UEFI . :

- UEFI- /boot/efi;
- UEFI- grub2;
- /boot/efi/EFI/astralinuxse/grubx64.efi;

UEFI .

efibootmgr. UEFI-:

```
sudo efibootmgr
```

```
BootCurrent: 0004
Timeout: 0 seconds
BootOrder: 0004,0000,0001,0002,0003
Boot0000* UiApp
Boot0001* UEFI VBOX CD-ROM VB2-01700376
Boot0002* UEFI VBOX HARDDISK VBca27e834-16bf61c9
Boot0003* EFI Internal Shell
Boot0004* astralinuxse
```

UEFI- grub2

, grub2, (/vmlinuz /initrd.img) UEFI, . :

```
#!/bin/bash
sudo mkdir /boot/efi/EFI/astralinuxefi
sudo cp /vmlinuz /boot/efi/EFI/astralinuxefi
sudo cp /initrd.img /boot/efi/EFI/astralinuxefi
export UUID=$(sudo blkid -s UUID -o value /dev/sda2)
sudo efibootmgr -c -g -L "astralinuxefi" -l '\EFI\astralinuxefi\vmlinuz' -u "root=UUID=$UUID rw quiet
rootfstype=ext4 add_efi_memmap initrd=\\EFI\\astralinuxefi\\initrd.img"
```

, /dev/sda2. /boot/efi/EFI/astralinuxefi, , efibootmgr .
, /dev/sda (, /dev/vda QEMU), -d:

```
sudo efibootmgr
```

```
sudo efibootmgr -d /dev/vda ...
```

```
efibootmgr (Boot0005):
```

```
sudo efibootmgr
```

```
BootCurrent: 0004
Timeout: 0 seconds
BootOrder: 0005,0004,0000,0001,0002,0003
Boot0000* UiApp
Boot0001* UEFI VBOX CD-ROM VB2-01700376
Boot0002* UEFI VBOX HARDDISK VBca27e834-16bf61c9
Boot0003* EFI Internal Shell
Boot0004* astralinuxse
Boot0005* astralinuxefi
```

```
( BootCurrent 0005):
```

```
sudo efibootmgr
```

```
BootCurrent: 0005
Timeout: 0 seconds
BootOrder: 0005,0004,0000,0001,0002,0003
Boot0000* UiApp
Boot0001* UEFI VBOX CD-ROM VB2-01700376
Boot0002* UEFI VBOX HARDDISK VBca27e834-16bf61c9
Boot0003* EFI Internal Shell
Boot0004* astralinuxse
Boot0005* astralinuxefi
```

```
:
```

```
sudo efibootmgr -B -b 4
```

UEFI

, , UEFI, efibootmgr, /sys/firmware/efi, UEFI. , :

```
ls -l /sys/firmware/efi
```

UEFI

UEFI efibootmgr (). man:

```
man efibootmgr
```

UEFI

Virtual Machine Manager

```
- " ", "".
```

"Firmware" UEFI-. , ".ms" "secureboot". "UEFI x84_64 /usr/share/OVMF/OVMF_CODE_4m.fd".

"" "".

Oracle VirtualBox

Oracle VM VirtualBox : "" - "" - " " - - " EFI ().