

OEM

- OEM-
 - OEM
 - OEM Astra Linux Common Edition Astra Linux Special Edition x.7
 - OEM Astra Linux Special Edition .10015-01 1.6
 - -
 -
 -
 -
 - OEM
-
-



:

- Astra Linux Special Edition .10015-01 (1.7), .10015-10
- Astra Linux Special Edition .10015-17
- Astra Linux Special Edition .10015-37 (7.7)
- Astra Linux Special Edition .10015-03 (7.6)
- Astra Linux Special Edition .10152-02 (4.7)
- Astra Linux Special Edition .10015-01 (1.6) [20200327SE16 \(5\)](#)
- Astra Linux Special Edition .10015-16 . 1 [20201007SE16](#)
- Astra Linux Common Edition 2.12



, () , .
 , () , , .



astra-installer :

- Astra Linux Special Edition .10015-01 (x.7)
- Astra Linux Common Edition 2.12.29

Astra Linux astra-installer «->. , OEM .

1. (OEM-):
 - a. (). -;
 - b. OEM ;
 - c. OEM;
 - d. ;
2. (,) OEM, , , . - - .

OEM-

- Astra Linux, . , -, . - , .

OEM

.

OEM Astra Linux Common Edition Astra Linux Special Edition x.7

OEM astra-installer. Astra Linux Common Edition 2.12.29 Astra Linux Special Edition x.7 astra-installer :

```
sudo apt install astra-installer-qt-oem-integration
```

Astra Linux Common Edition .

OEM Astra Linux Special Edition .10015-01 1.6

OEM Astra Linux Special Edition .10015-01 1.6:

- [20200327SE16 \(5\)](#) ();
- ():
 - python3-babel;
 - python3-yaml;
- [xkbgroup](#), Astra Linux Special Edition.

:

1. [20200327SE16 \(5 \)](#) ();
2. Astra Linux Common Edition:
 - a. Astra Linux Common Edition ([Astra Linux](#)) Astra Linux Common Edition.
 - b. :

```
sudo apt -f install
```

3. Astra Linux Common Edition :
 - a. , ();
 - b. python3-babel, python3-yaml:

```
sudo apt install python3-babel python3-yaml
```

- c. WEB- [xkbgroup](#), Astra Linux Special Edition, :

```
sudo dpkg -i ~/xkbgroup_0.2.0-1astra4_amd64.deb
```

- d. WEB- [astra-installer-smolensk-1.9.2.tar.gz](#), :

```
cd ~/
tar -xvzf astra-installer-smolensk-*.tar.gz
sudo dpkg -i astra-installer*.deb
```

- e. :

```
sudo apt -f install
```

OEM ""->">" ""->">">">">" " :

```
sudo astra-installer-qt-oem
```

OEM , , , , , .

- "" ,
- .

 " " " " , OEM .

"" , OEM .

• , , , , , .





, , "" .

OEM

OEM " OEM" ""->" "->"", :

```
sudo astra-installer-qt-oem-integration
```

" ", , .



OEM , , , .

, , ().

OEM , . Network Manager Applet.



, , " OEM" :




/etc/fly-kiosk/astra-admin.

OEM.

:

- " ",
- ,
- ,
- ,
- ,
- ,
- ,

, OEM :



/var/log/astra-installer.log. (/proc/cmdline, /proc/cpuinfo, lsblk ..) /var/log/astra-installer/start. /var/log/astra-installer/finish.