



# fly-admin-screen

fly-admin-screen    Astra Linux    :

- (" - " - " - ");
- ;
- 

fly-admin-screen



## /etc/X11/xorg.conf

/etc/X11/xorg.conf    ,    ( , ).    .

```
Section "ServerLayout"

    Identifier "X.org Configured"
    Screen 0 "Screen0" 0 0

    InputDevice "Mouse0" "CorePointer"

    InputDevice "Keyboard0" "CoreKeyboard"

EndSection

Section "Files"

    ModulePath "/usr/lib/xorg/modules"

    FontPath "/usr/share/fonts/X11/misc"

    FontPath "/usr/share/fonts/X11/100dpi/:unscaled"

    FontPath "/usr/share/fonts/X11/75dpi/:unscaled"

    FontPath "/usr/share/fonts/X11/Type1"

    FontPath "/usr/share/fonts/X11/100dpi"

    FontPath "/usr/share/fonts/X11/75dpi"

    FontPath "/usr/share/fonts/msttcorefonts"

    FontPath "built-ins"

EndSection

Section "Module"

    Load "record"
```

```

Load "dri"

Load "dri2"

Load "extmod"

Load "dbe"

Load "glx"

EndSection

Section "InputDevice"

    Identifier "Keyboard0"

    Driver "kbd"

    Option "XkbLayout" "us,ru"

    Option "XkbOptions" "grp:ctrl_shift_toggle"

EndSection

Section "InputDevice"

    Identifier "Mouse0"

    Driver "mouse"

    Option "Protocol" "auto"

    Option "Device" "/dev/input/mice"

    # Option "ZAxisMapping" "4 5 6 7"

EndSection

Section "Monitor"

    Identifier "MonitorLVDS"

    # VendorName "Monitor Vendor"

    ModelName "Monitor Model"

    Option "DPMS" "False"

    Option "Position" "0 0"

EndSection

Section "Monitor"

    Identifier "MonitorVGA"

    # VendorName "Monitor Vendor"

    ModelName "Monitor Model"

    Option "DPMS" "False"

    Option "RightOf" "MonitorLVDS"

    Option "Position" "1280 0"

    #Option "Position" "1366 0" # Position

EndSection

Section "Device"

    ### Available Driver options are:-

    ### Values: <i>: integer, <f>: float, <bool>: "True"/"False",

    ### <string>: "String", <freq>: "<f> Hz/kHz/MHz"

    ### [arg]: arg optional

```

```

#Option "ColorKey" # <i>
#Option "Dac6Bit" # [<bool>]
Option "DRI" "True" # [<bool>]
#Option "NoDDC" # [<bool>]
#Option "ShowCache" # [<bool>]
#Option "PageFlip" # [<bool>]
Option "Tiling" "True"
Option "XvPreferOverlay" "True"
Option "FallbackDebug" "False"
Option "XvMC" "True"
Identifier "Card0"
Driver "intel"
VendorName "Intel Corporation"
BoardName "Core Processor Integrated Graphics Controller"
BusID "PCI:0:2:0"
Option "monitor-VGA1" "MonitorLVDS"
Option "monitor-HDMI1" "MonitorVGA" # /var/log/Xorg.log.0
monitor-HDMI1 monitor-VGA1 # monitor-DP1 monitor-DP2 monitor-HDMI2
EndSection

Section "Screen"

    Identifier "Screen0"

    Device "Card0"

    Monitor "MonitorLVDS"

    SubSection "Display"

        Viewport 0 0

        Depth 24

        # Modes "1366x768" # 1 Modes "1280x1024"

    EndSubSection

EndSection

Section "Screen"

    Identifier "Screen0"

    Device "Card0"

    Monitor "MonitorVGA"

    SubSection "Display"

        Viewport 0 0 Depth 24

        #Modes "1280x1024" # 2 Modes "1680x1050"

    EndSubSection

EndSection

```

[acer\\_2monitor\\_config\(1\).tgz](#)

1360x768.

cvt:

```
cvt 1360 768 60
```

:



Modeline "1360x768\_60.00" 84.75 1360 1432 1568 1776 768 771 781 798 -hsync +vsync

Modeline :

```
#  
xrandr --newmode "1360x768_60.00" 84.75 1360 1432  
1568 1776 768 771 781 798 -hsync +vsync
```

```
#  
xrandr --addmode VGA-0 1360x768_60.00
```

```
#  
xrandr --output VGA-0 --mode 1360x768_60.00
```

.