

-
- FreeIPA
- Windows AD
 - astra-ad-sssd-client
 - astra-winbind



:


- Astra Linux Special Edition .10015-01 (1.7), .10015-10
- Astra Linux Special Edition .10015-17
- Astra Linux Special Edition .10015-37 (7.7)




1. " ":

```
sudo fly-admin-dm
```

2. "":



3. " :



4. ()

5. $\frac{1}{2} \frac{1}{2}$, $\frac{1}{2}$;

6. .

FreeIPA

• •

1. FreeIPA:

a. , :

```
kinitt admin
```

b. web- FreeIPA :

```
ipa idrange-find
-----
1
-----
: IPADOMAIN0.RU_id_range
  POSIX : 1899200000
        : 200000
  RID    RID: 1000
  RID    RID: 100000000
        : local domain range
```

-----[domain/<_>)]

1

1 899 200 000 200 000 , . 1 899 200 000 1 899 399 999;

2. :

a. sssd, /etc/sssds/sssds.conf FreeIPA ([domain/<_>)] :


enumerate = true

b. " ":

sudo fly-admin-dm

c. "";

d. " " , : :



e. "" "" , ;

f. .

Windows AD

astra-ad-sssds-client

1. sssd /etc/sssds/sssds.conf [domain] :

enumerate = True

2. sssd:

sudo systemctl restart sssd

astra-winbind



winbind, . sssd.

1. samba/etc/samba/smb.conf winbind use default domain winbind enum users yes:

```
winbind use default domain = yes  
winbind enum users = yes
```

2. winbind:

```
sudo systemctl restart winbind.service
```