

pcscd

- 1
- 2: - PC/SC ().
- 3
- 4
- 5



:

- Astra Linux Special Edition .10015-01 (1.7)
- Astra Linux Special Edition .10015-17
- Astra Linux Special Edition .10015-37 (7.7)
- Astra Linux Special Edition .10015-03 (7.6)
- Astra Linux Special Edition .10152-02 (4.7)
- Astra Linux Special Edition .10015-01 (1.6)
- Astra Linux Special Edition .10015-16 . 1
- Astra Linux Special Edition .10015-16 . 2
- Astra Linux Special Edition .10265-01 (8.1)
- Astra Linux Common Edition 2.12

Astra Linux Special Edition .10015-10

: - PC/SC ().

: PC/SC / - « » .

pcscd pcscd.socket PARSEC_CAP_PRIV_SOCKET (. PARSEC). :

1. :

```
sudo systemctl edit pcscd.socket
```

2. :

```
[Socket]
CapabilitiesParsec=PARSEC_CAP_PRIV_SOCKET
```

3. ;

4. :

```
sudo systemctl restart pcscd.socket
```

pcscd.socket, ehole. :

```
sudo pdp-ls -Ma /var/run/pcscd/pcscd.comm
```

:

```
srw-rw-rw-m-- 1 root root _0:::ehole /var/run/pcscd/pcscd.comm
```

ehole, pcscd.comm :

```
sudo rm -r /var/run/pcscd/pcscd.comm
```

. opensc-explorer.

Astra Linux Special Edition x.7 pdp-exec:

```
sudo pdp-exec -l 1:0:0 opensc-explorer
```

opensc-explorer .

Opensc explorer, :

```
root@smolensk: # opensc-explorer
OpenSC Explorer version 0.16.0
Using reader with a card: Aktiv Rutoken ECP 00 00
OpenSC [3F00]>
```

pcscd . :

1. :

```
sudo systemctl edit pcscd.service
```

2. [Service] ,, :

```
[Service]
PDPLabel=1:63:0
```



:
PDPLabel=<>:< >:<>
PDPLabel PARSEC - .

3. ;

4. :

```
sudo systemctl restart pcscd.service
```