

DHCP

-
- IP MAC-
- DNS FreeIPA

Astra Linux [DHCP](#)- isc-dhcp-server fly-admin-dhcp. fly-admin-dhcp (. [synaptic](#)), :

```
sudo apt install fly-admin-dhcp
```

```
fly-admin-dhcp    isc-dhcp-server.    ("'" > '"' > "'" > "DHCP"),    .
```

```
DHCP /etc/default/isc-dhcp-server /etc/dhcp/dhcpd.conf. /etc/default/isc-dhcp-server INTERFACES , . ,
. ( IPv4 eth0, IPv6):
```


ip a

```
/etc/dhcp/dhcpd.conf , DHCP .
```


nmap:

```
sudo apt install nmap
sudo nmap --script broadcast-dhcp-discover localhost
```

•

```
cat /var/lib/dhcp/dhcpd.lease
```

DNS:-

 option domain-name "somedomain.example.com";
option domain-name-servers 10.0.2.254;

- filename -
- next-server - , (IP-)

:

 subnet 10.0.2.0 netmask 255.255.255.0 {
 range 10.0.2.10 10.0.2.100;
 max-lease-time 86400;
 option routers 10.0.2.1;
 filename "pxelinux.0";
 next-server 10.0.2.254;
}

IP MAC-

 host hostname1 {hardware ethernet 52:54:00:36:8f:d1; fixed-address 10.0.2.10;}
host hostname2 {hardware ethernet 52:54:00:a0:b1:c2; fixed-address 10.0.2.11;}

 host hostname1 {hardware ethernet 52:54:00:36:8f:d1; fixed-address hostname1.example.com;}
host hostname2 {hardware ethernet 52:54:00:a0:b1:c2; fixed-address hostname2.example.com;}

DHCP IPv4 fly-admin-dhcp.

 **DHCP**
: /etc/dhcp/dhcpd.conf authoritative. , , (), .

:

```
sudo systemctl restart isc-dhcp-server
```

DNS FreeIPA

DHCP DNS- FreeIPA . [DNS FreeIPA](#)