

Astra Linux Special Edition 1.5 ALD

1.44, 1.5

Astra Linux Special Edition .10015-01 (1.4) :
ald-init init

Astra Linux Special Edition .10015-01 (1.5) :

- /etc/ald/ald.conf VERSION 1.7 1.5:

VERSION=1.5

- /etc/ald/ald.conf USE_RPC, :

USE_RPC=0

- .:

ald-client join dcm14

:

- Astra Linux Special Edition .10015-01 (1.5) -. .
- local

1.5, 1.4

Astra Linux Special Edition .10015-01 (1.5) :

/etc/ald/config-templates/kdc.conf

- gost-cts:normal
- master_key_type gost-cts aes256-cts

master_key_type = aes256-cts

/etc/ald/config-templates/krb5.conf

- : default_tgs_enctypes, default_tkt_enctypes, permitted_enctypes gost-cts

default_tgs_enctypes = aes256-cts des-cbc-crc rc4-hmac
default_tkt_enctypes = aes256-cts des-cbc-crc rc4-hmac
permitted_enctypes = aes256-cts des-cbc-crc rc4-hmac

- /etc/ald/ald.conf VERSION 1.7 1.5:

VERSION=1.5

- /etc/ald/ald.conf USE_RPC, :

USE_RPC=0

- .:

ald-init init

Astra Linux Special Edition .10015-01 (1.4) (sudcm.rtfm.rbt):
ald-client join sudcm

Astra Linux Special Edition .10015-01 (1.4), , . Astra Linux Special Edition .10015-01 (1.5) (ac14.rtfm.rbt):
kadmin.local -q "modprinc +requires_preauth host/ac14.rtfm.rbt"

aldd:
service aldd restart