Samba

, :

/etc/samba/smb.conf

```
[global]

   workgroup = WORKGROUP
   server string = Media Server
   security = user
   map to guest = Bad User
   log file = /var/log/samba/%m.log
   max log size = 50
   guest account = nobody
   dns proxy = no

[share]

   path = /var/lib/samba/share
   guest ok = yes
   public = yes
   writable = yes
   available = yes
```

0775 nobody, nogroup:

```
sudo chown nobody:nogroup /var/lib/samba/share

sudo chmod 0775 /var/lib/samba/share
```

`cifs-utils`

```
sudo apt-get install cifs-utils
```

( ) , :

```
sudo mount -t cifs //10.0.10.201/share /mnt -o users,sec=none
```

, Windows Astra Linux, "share":

```
create mask = 0777

directory mask = 0777

force create mode = 777

force directory mode = 777
```