

xorg.conf

/etc/X11/xorg.conf , (,). .

Section "ServerLayout"

Identifier "X.org Configured" Screen 0 "Screen0" 0 0

InputDevice "Mouse0" "CorePointer"

InputDevice "Keyboard0" "CoreKeyboard"

EndSection

Section "Files"

ModulePath "/usr/lib/xorg/modules"

FontPath "/usr/share/fonts/X11/misc"

FontPath "/usr/share/fonts/X11/100dpi:unscaled"

FontPath "/usr/share/fonts/X11/75dpi:unscaled"

FontPath "/usr/share/fonts/X11/Type1"

FontPath "/usr/share/fonts/X11/100dpi"

FontPath "/usr/share/fonts/X11/75dpi"

FontPath "/usr/share/fonts/msttcorefonts"

FontPath "built-ins"

EndSection

Section "Module"

Load "record"

Load "dri"

Load "dri2"

Load "extmod"

Load "dbe"

Load "glx"

EndSection

Section "InputDevice"

Identifier "Keyboard0"

Driver "kbd"

Option "XkbLayout" "us,ru"

Option "XkbOptions" "grp:ctrl_shift_toggle"

EndSection

Section "InputDevice"

Identifier "Mouse0"

Driver "mouse"

Option "Protocol" "auto"

Option "Device" "/dev/input/mice"

Option "ZAxisMapping" "4 5 6 7"

EndSection

Section "Monitor"

```

Identifier "MonitorLVDS"

# VendorName "Monitor Vendor"

ModelName "Monitor Model"

Option "DPMS" "False"

Option "Position" "0 0"

EndSection

Section "Monitor"

Identifier "MonitorVGA"

# VendorName "Monitor Vendor"

ModelName "Monitor Model"

Option "DPMS" "False"

Option "RightOF" "MonitorLVDS"

Option "Position" "1280 0"

#Option "Position" "1366 0" # Position

EndSection

Section "Device"

### Available Driver options are:-

### Values: <i>: integer, <f>: float, <bool>: "True"/"False",

### <string>: "String", <freq>: "<f> Hz/kHz/MHz"

### [arg]: arg optional

#Option "ColorKey" # <i>

#Option "Dac6Bit" # [<bool>]

Option "DRI" "True" # [<bool>]

#Option "NoDDC" # [<bool>]

#Option "ShowCache" # [<bool>]

#Option "PageFlip" # [<bool>]

Option "Tiling" "True"

Option "XvPreferOverlay" "True"

Option "FallbackDebug" "False"

Option "XvMC" "True"

Identifier "Card0"

Driver "intel"

VendorName "Intel Corporation"

BoardName "Core Processor Integrated Graphics Controller"

BusID "PCI:0:2:0"

Option "monitor-VGA1" "MonitorLVDS"

Option "monitor-HDMI1" "MonitorVGA" # /var/log/Xorg.log.0 , monitor-HDMI1 monitor-VGA1 # monitor-
DP1 monitor-DP2 monitor-HDMI2

EndSection

Section "Screen"

```

```

Identifier "Screen0"

Device "Card0"

Monitor "MonitorLVDS"

SubSection "Display"

    Viewport 0 0

    Depth 24

    # Modes "1366x768" #    1 Modes "1280x1024"

EndSubSection

EndSection

```

```

Section "Screen"

    Identifier "Screen0"

    Device "Card0"

    Monitor "MonitorVGA"

    SubSection "Display"

        Viewport 0 0 Depth 24

        #Modes "1280x1024" #    2 Modes "1680x1050"

    EndSubSection

EndSection

```

[acer_2monitor_config\(1\).tgz](#)

1360x768 :

```
cvt 1360 768 60
```

:

```

xrandr --newmode "1360x768_60.00" 84.75 1360 1432 1568 1776 768 771 781 798 -hsync +vsync
xrandr --addmode VGA-0 1360x768_60.00
xrandr --output VGA-0 --mode 1360x768_60.00

```